

How to Adjust the High DPI Settings When Using a 4K or Hi-Resolution Screen

Last Modified on 06/06/2023 5:17 pm EDT

How to Adjust the High DPI Settings When Using a 4K or Hi-Resolution Screen

It is possible when using a 4K or high-resolution display or laptop, you may need to adjust the High DPI scaling for best performance when using and viewing the URC Accelerator 3, TC Flex 2 and Complete Control Program programs.


This article details the steps required to adjust you laptop or PC for this situation.

Note: This articles details a Windows 10 OS installation


Step #1:

Navigate to: *C:\Program Files (x86)\Universal Remote Control, Inc\URC Accelerator 3* as shown below:


(or... *URC Accelerator2/Total Control Flex 2/Complete Control Program*. This file path may vary based on the URC program you need to adjust).



Alternately, you can also right-click on the desktop shortcut for the appropriate URC program. This shortcut is usually on your PC desktop after a standard installation.




Step #2: Right click on the **URC Accelerator 3** shortcut (or the appropriate URC program shortcut) and then select Properties (as shown below):



Step #3:


Click the **Compatibility** tab and then the **Change high DPI settings** (as shown below):



Step #4:

Check the box for: **Override high DPI scaling behavior...**

In the drop down for: **Scaling Performed By:** choose Application, System or System (Enhanced). In most cases, System (Enhanced) yields the best results but this may require some experimentation depending on your specific laptop or PC system configuration (see image below):



Additional Information & Resources:

To learn more about Accelerator 3 configuration and programming, please see the Accelerator 3 online [Programming Guide](#).
