

How to Adjust the High DPI Settings When Using a 4K or Hi-Resolution Screen

Last Modified on 06/09/2021 10:30 am EDT

How to Adjust the High DPI Settings When Using a 4K or Hi-Resolution Screen

It is possible when using a 4K or high-resolution display or laptop, you may need to adjust the High DPI scaling for best performance when using and viewing the URC Accelerator 3, TC Flex 2 and Complete Control Program programs.


This article details the steps required to adjust you laptop or PC for this situation.

Note: This articles details a Windows 10 OS installation

Step #1:


Navigate to: *C:\Program Files (x86)\Universal Remote Control, Inc\URC Accelerator 3* as shown below: (or...*URC Accelerator 2/Total Control Flex 2/Complete Control Program*. This file path may vary based on the URC program you need to adjust).

Alternately, you can also right-click on the desktop shortcut for the appropriate URC program. This shortcut is usually on your PC desktop after a standard installation.




Step #2:

Right click on the **URC Accelerator 3** shortcut (or the appropriate URC program shortcut) as shown below:



Step #3:


Click the **Compatibility** tab and then the **Change high DPI settings** as shown below:



Step #4:

Check the box for: **Override high DPI scaling behavior...**

In the drop down for: Scaling Performed By: choose Application, System or System (Enhanced). In most cases, System (Enhanced) yields the best results but this may require some experimentation depending on your specific system configuration (see image below):



Additional Information & Resources:

Please refer to this article on [How to Adjust Accelerator Options](#) in Accelerator 3.
